

Aug 2016

## **Contents**

1	File	Index			1
	1.1	File Lis	st		1
2	File	Docum	entation		3
	2.1	QuickN	/lotionDete	ector.h File Reference	3
		2.1.1	Detailed	Description	3
		2.1.2	Function	Documentation	3
			2.1.2.1	QuickMotionDetectorDestroy	4
			2.1.2.2	QuickMotionDetectorExecute	4
			2.1.2.3	QuickMotionDetectorInitialize	4
Inc	lex				5

# Chapter 1

## File Index

#### QuickMotionDetector.h

2 File Index

### **Chapter 2**


### **File Documentation**

#### 2.1 QuickMotionDetector.h File Reference

Header file for HawXeye's Quick Motion Detection engine.

#include <stdint.h>

Include dependency graph for QuickMotionDetector.h:



#### **Functions**

- int32\_t QuickMotionDetectorInitialize (const char \*configFileName)

  Initialize Quick Motion Detection engine.
- int32\_t QuickMotionDetectorExecute (bool \*detected, unsigned char \*frame, uint32\_t width, uint32\_t height)

  Execute the core functionality of Quick Motion Detection.
- int32\_t QuickMotionDetectorDestroy ()

Destroy Quick Motion Detection engine.

#### 2.1.1 Detailed Description

Copyright

2016 HawXeye, Inc. All rights reserved.

#### 2.1.2 Function Documentation

4 File Documentation

#### 2.1.2.1 int32\_t QuickMotionDetectorDestroy ( )

#### Returns

RETURN\_SUCCESS upon successful execution, and RETURN\_FAILURE upon failure.

2.1.2.2 int32\_t QuickMotionDetectorExecute ( bool \* detected, unsigned char \* frame, uint32\_t width, uint32\_t height )

This function performs object detection using the input 8-bit Y-component frame. Once an object is detected, this function will continue to return true.

#### **Parameters**

out	detected	TRUE if an object was detected.	
in	frame	component frame to run object detection on.	
in	width	width of the frame in pixels.	
in	height	height of the frame in pixels.	

#### Returns

RETURN\_SUCCESS upon successful execution, and RETURN\_FAILURE upon failure.

#### 2.1.2.3 int32\_t QuickMotionDetectorInitialize ( const char \* configFileName )

#### **Parameters**

in	configFileName	path to client configuration XML file
	0	1

#### Returns

RETURN\_SUCCESS upon successful execution, and RETURN\_FAILURE upon failure.

### Index

QuickMotionDetector.h, 3
QuickMotionDetectorDestroy, 3
QuickMotionDetectorExecute, 4
QuickMotionDetectorInitialize, 4
QuickMotionDetectorDestroy
QuickMotionDetector.h, 3
QuickMotionDetectorExecute
QuickMotionDetector.h, 4
QuickMotionDetectorInitialize

QuickMotionDetector.h, 4